

# Uninstalling xCAT2.X

01/07/10, 10:59:06 AM

## Table of Contents

<a href="#">1.0 Removing xCAT2.X</a>	1
<a href="#">1.1 Backup you xCAT database ( if you want to keep it)</a>	1
<a href="#">1.2 Stop xcatd</a>	1
<a href="#">1.3 Remove xCAT rpms</a>	1
<a href="#">1.4 Optionally, Remove OSS prerequisites installed for xCAT</a>	2
<a href="#">1.5 Optionally, Remove root ssh keys</a>	2
<a href="#">1.6 Remove xCAT credentials</a>	2
<a href="#">1.7 Remove xCAT data directories</a>	2
<a href="#">1.8 Remove xCAT install Directories</a>	3
<a href="#">1.9 Remove Extraneous files</a>	3
<a href="#">1.10 Remove Postgresql Database</a>	3
<a href="#">1.11 Remove MySQL Database</a>	3

## 1.0 Removing xCAT2.X

### 1.1 Backup you xCAT database ( if you want to keep it)

```
dumpxCATdb -p <path to where to save the database>
```

### 1.2 Stop xcatd

For Linux:

```
Service xcatd stop
```

For AIX:

```
xcatstop
```

### 1.3 Remove xCAT rpms

Run `rpm -qa | grep xCAT` and remove the rpms output as in the example:

- xCAT-nbkernel-x86\_64-2.6.18\_92-4.noarch
- xCAT-nbkernel-ppc64-2.6.18\_92-4.noarch
- xCAT-nbroot-oss-x86\_64-2.0-snap200801291344.noarch
- xCAT-web-2.2-snap200904011710.noarch
- xCAT-server-2.3-snap200907061256.noarch
- xCAT-rmc-2.3-snap200905291339.noarch
- xCAT-2.3-snap200907061256.x86\_64

- xCAT-nbroot-core-ppc64-2.3-snap200907061256.noarch
- xCAT-nbkernel-x86-2.6.18\_92-4.noarch
- xCAT-nbroot-oss-x86-2.0-snap200804021050.noarch
- xCAT-nbroot-oss-ppc64-2.0-snap200801291320.noarch
- xCAT-client-2.3-snap200907061256.noarch
- perl-xCAT-2.3-snap200907061256.noarch
- xCAT-nbroot-core-x86-2.3-snap200907061256.noarch
- xCAT-nbroot-core-x86\_64-2.2-snap200904010841.noarch

#### **1.4 Optionally, Remove OSS prerequisites installed for xCAT**

- rpm -e fping-2.2b1-1
- rpm -e perl-Digest-MD5-2.36-1
- rpm -e perl-Net\_SSLeay.pm-1.30-1
- rpm -e perl-IO-Socket-SSL-1.06-1
- rpm -e perl-IO-Stty-.02-1
- rpm -e perl-IO-Tty-1.07-1
- rpm -e perl-Expect-1.21-1
- rpm -e conserver-8.1.16-2
- rpm -e expect-5.42.1-3
- rpm -e tk-8.4.7-3
- rpm -e tcl-8.4.7-3
- rpm -e perl-DBD-SQLite-1.13-1
- rpm -e perl-DBI-1.55-1

#### **1.5 Optionally, Remove root ssh keys**

- rm -rf \$ROOTHOME/ssh

#### **1.6 Remove xCAT credentials**

- rm -rf \$ROOTHOME/.xcat

#### **1.7 Remove xCAT data directories**

For Linux:

- rm -rf /install (for AIX this include the nim directory with images which you may not want to remove)

For AIX or Linux:

- rm -rf /tftpboot/xcat\*
- rm -rf /tftpboot/etc
- rm -rf /etc/xcat
- rm -rf /etc/sysconfig/xcat ( may not exist)
- rm /mnt/xcat

## **1.8 Remove xCAT install Directories**

- `rm -rf $ROOTHOME/xcat2`

## **1.9 Remove Extraneous files**

- `/tmp/genimage*`
- `/tmp/packimage*`
- `/tmp/mknb*`
- `/etc/yum.repos.d/*`

## **1.10 Remove Postgresql Database**

- `su - postgres`
- `dropdb -h 11.16.0.1 -i -e --username xcatadmin xcatdb`
- Database "xcatdb" will be permanently removed.
- Are you sure? (y/n) y
- Password:
- `DROP DATABASE xcatdb;`
- `DROP DATABASE`
- `service postgresql stop`

## **1.11 Remove MySQL Database**

See [MySQL documentation](#) for removing the database.